

Can strace make you fail?

strace syscall fault injection

Dmitry Levin

FOSDEM 2017

What is strace?

- A diagnostic, debugging and instructional userspace utility for Linux.
- It is used to monitor interactions between processes and the Linux kernel, which include system calls, signal deliveries, and changes of process state.
- CLI and multiple filtering capabilities make it a powerful yet easy to use tracing tool.
- Last year strace has been extended to tamper with traces using syscall fault injection.

sample output

```
$ strace -s 0 -P /dev/urandom python3 < /dev/null
open("/dev/urandom", O_RDONLY|O_CLOEXEC) = 3
fcntl(3, F_GETFD) = 0x1 (flags FD_CLOEXEC)
read(3, "...", 24) = 24
close(3) = 0
+++ exited with 0 +++
```

What is fault injection?

- a software testing technique
- used for improving test coverage
- of error handling code paths
- that might otherwise rarely be followed
- by introducing faults

Where to place strace among other fault injection tools?

- software
- runtime
- syscall interposition
- userspace
- unprivileged
- command-line interface

strace syscall fault injection syntax

```
strace -e trace=open cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = 3
+++ exited with 0 +++
```

```
strace -e trace=open -e fault=open cat
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = -1 ENOSYS (Function not implemented) (INJECTED)
open("/lib64/tls/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOSYS (Function not implemented) (INJECTED)
open("/lib64/tls/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOSYS (Function not implemented) (INJECTED)
open("/lib64/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOSYS (Function not implemented) (INJECTED)
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOSYS (Function not implemented) (INJECTED)
cat: error while loading shared libraries: libc.so.6: cannot open shared object file: Error 38
+++ exited with 127 +++
```

strace syscall fault injection syntax

```
strace -e trace=open cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = 3
+++ exited with 0 +++
```

```
strace -e trace=open -e fault=open:error=ENOENT
cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or direc
open("/lib64/tls/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such fi
open("/lib64/tls/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or d
open("/lib64/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file o
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or direc
open("/usr/lib64/tls/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No suc
open("/usr/lib64/tls/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file
open("/usr/lib64/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such fi
open("/usr/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or d
cat: error while loading shared libraries: libc.so.6: cannot open shared object
+++ exited with 127 +++
```

strace syscall fault injection syntax

```
strace -e trace=open cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY)                = 3
+++ exited with 0 +++
```

```
strace -e trace=open
-e fault=open:when=1:error=EACCES cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = -1 EACCES (Permission denied) (INJECTED)
open("/lib64/tls/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or directory)
open("/lib64/tls/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or directory)
open("/lib64/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or directory)
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY)                = 3
+++ exited with 0 +++
```

strace syscall fault injection syntax

```
strace -e trace=open cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = 3
+++ exited with 0 +++
```

```
strace -e trace=open
-e fault=open:when=2+:error=EPERM cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)
open("/lib64/tls/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)
open("/lib64/tls/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)
open("/lib64/x86_64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)
cat: error while loading shared libraries: libc.so.6: cannot open shared object file: Operation not permitted
+++ exited with 127 +++
```

```
strace -e trace=open cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = 3
+++ exited with 0 +++
```

```
strace -a30 -e trace=open
-e fault=open:when=3:error=EACCES cat /dev/null
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = -1 EACCES (Permission denied) (INJECTED)
cat: /dev/null: Permission denied
+++ exited with 1 +++
```


strace syscall fault injection syntax

```
strace -a30 -e trace=open cat /dev/null{,}{,}
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = 3
open("/dev/null", O_RDONLY) = 3
open("/dev/null", O_RDONLY) = 3
open("/dev/null", O_RDONLY) = 3
+++ exited with 0 +++
```

```
strace -a30 -e trace=open
-e fault=open:when=3+2:error=EACCES
cat /dev/null{,}{,}
```

```
open("/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
open("/lib64/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
open("/dev/null", O_RDONLY) = -1 EACCES (Permission denied) (INJECTED)
cat: /dev/null: Permission denied
open("/dev/null", O_RDONLY) = 3
open("/dev/null", O_RDONLY) = -1 EACCES (Permission denied) (INJECTED)
cat: /dev/null: Permission denied
open("/dev/null", O_RDONLY) = 3
+++ exited with 1 +++
```

strace -P /dev/null cat /dev/null

```
open("/dev/null", O_RDONLY) = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072) = 0
close(3) = 0
+++ exited with 0 +++
```

strace -a28 -P /dev/null -e fault=file cat /dev/null

```
open("/dev/null", O_RDONLY) = -1 ENOSYS (Function not implemented) (INJECTED)
cat: /dev/null: Function not implemented
+++ exited with 1 +++
```

```
strace -a25 -P /dev/null cat /dev/null
```

```
open("/dev/null", O_RDONLY) = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072)      = 0
close(3)                 = 0
+++ exited with 0 +++
```

```
strace -a25 -P /dev/null -e fault=fstat:error=ENOMEM
cat /dev/null
```

```
open("/dev/null", O_RDONLY) = 3
fstat(3, 0x7ffd970bb080) = -1 ENOMEM (Cannot allocate memory) (INJECTED)
cat: /dev/null: Cannot allocate memory
close(3)                 = 0
+++ exited with 1 +++
```

strace -P /dev/null cat /dev/null

```
open("/dev/null", O_RDONLY)          = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072)                  = 0
close(3)                              = 0
+++ exited with 0 +++
```

strace -P /dev/null -e fault=*fadvise64* cat /dev/null

```
open("/dev/null", O_RDONLY)          = 3
fstat(3, st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = -1 ENOSYS (Function not implemented) (INJECTED)
read(3, "", 131072)                  = 0
close(3)                              = 0
+++ exited with 0 +++
```

strace -P /dev/null cat /dev/null

```
open("/dev/null", O_RDONLY) = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072) = 0
close(3) = 0
+++ exited with 0 +++
```

strace -a32 -P /dev/null -e fault=read:error=EIO cat /dev/null

```
open("/dev/null", O_RDONLY) = 3
fstat(3, st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, 0x7f057432c000, 131072) = -1 EIO (Input/output error) (INJECTED)
cat: /dev/null: Input/output error
close(3) = 0
+++ exited with 1 +++
```

strace -P /dev/null cat /dev/null

```
open("/dev/null", O_RDONLY)           = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072)                   = 0
close(3)                               = 0
+++ exited with 0 +++
```

strace -a32 -P /dev/null -e fault=*read:when=1:error=EINTR* cat /dev/null

```
open("/dev/null", O_RDONLY)           = 3
fstat(3, st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, 0x7f057432c000, 131072) = -1 EINTR (Interrupted system call) (INJECTED)
read(3, "", 131072)                   = 0
close(3)                               = 0
+++ exited with 0 +++
```

strace syscall fault injection syntax

```
strace -a25 -P /dev/null cat /dev/null
```

```
open("/dev/null", O_RDONLY) = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072) = 0
close(3) = 0
+++ exited with 0 +++
```

```
strace -a25 -P /dev/null
-e fault=close:error=EINTR cat /dev/null
```

```
open("/dev/null", O_RDONLY) = 3
fstat(3, {st_mode=S_IFCHR|0666, st_rdev=makedev(1, 3), ...}) = 0
fadvise64(3, 0, 0, POSIX_FADV_SEQUENTIAL) = 0
read(3, "", 131072) = 0
close(3) = -1 EINTR (Interrupted system call) (INJECTED)
cat: /dev/null: Interrupted system call
+++ exited with 1 +++
```

examples: access control: path or descriptor arguments

```
strace -P /etc/passwd  
-e fault=file:error=EACCES -e fault=desc:error=EPERM  
stat . /etc/passwd > /dev/null
```

```
open("/etc/passwd", O_RDONLY|O_CLOEXEC) = -1 EPERM (Operation not permitted) (INJECTED)  
lstat("/etc/passwd", 0x7ffd282659d0) = -1 EACCES (Permission denied) (INJECTED)  
stat: cannot stat '/etc/passwd': Permission denied  
+++ exited with 1 +++
```

```
strace -a25 -P /etc/passwd -e fault=desc:error=EPERM  
cat < /etc/passwd
```

```
fstat(0, 0x7ffd6c14daa0) = -1 EPERM (Operation not permitted) (INJECTED)  
cat: -: Operation not permitted  
close(0) = -1 EPERM (Operation not permitted) (INJECTED)  
cat: closing standard input: Operation not permitted  
+++ exited with 1 +++
```


Error opening /dev/urandom

```
$ strace -P /dev/urandom -e fault=open:error=ENOENT python3 < /dev/null
open("/dev/urandom", O_RDONLY|O_CLOEXEC) = -1 ENOENT (No such file or dir
ectory) (INJECTED)
Fatal Python error: Failed to open /dev/urandom
--- SIGSEGV si_signo=SIGSEGV, si_code=SEGV_MAPERR, si_addr=0x50 ---
+++ killed by SIGSEGV +++
Segmentation fault
```

Error reading /dev/urandom

```
$ strace -a30 -P /dev/urandom -e fault=read:error=EIO python3 < /dev/null
open("/dev/urandom", O_RDONLY|O_CLOEXEC) = 3
fcntl(3, F_GETFD) = 0x1 (flags FD_CLOEXEC)
read(3, 0x8db610, 24) = -1 EIO (Input/output error) (INJECTED)
Fatal Python error: Failed to read bytes from /dev/urandom
--- SIGSEGV si_signo=SIGSEGV, si_code=SEGV_MAPERR, si_addr=0x50 ---
+++ killed by SIGSEGV +++
Segmentation fault
```

First mprotect invocation: without a proper check

```
$ strace -e mprotect -default=mprotect:when=1:error=EPERM pwd > /dev/null  
mprotect(0x7fabcd00f000, 2097152, PROT_NONE) = -1 EPERM (Operation not permitted) (INJECTED)  
mprotect(0x7fabcd20f000, 16384, PROT_READ) = 0  
mprotect(0x606000, 4096, PROT_READ) = 0  
mprotect(0x7fabcd441000, 4096, PROT_READ) = 0  
+++ exited with 0 +++
```

Second mprotect invocation: with a proper check

```
$ strace -e mprotect -default=mprotect:when=2+:error=EPERM pwd > /dev/null  
mprotect(0x7fabcd00f000, 2097152, PROT_NONE) = 0  
mprotect(0x7fabcd20f000, 16384, PROT_READ) = -1 EPERM (Operation not permitted) (INJECTED)  
pwd: error while loading shared libraries: /lib64/libc.so.6: cannot apply additional memory protection after relocation: Operation not permitted  
+++ exited with 127 +++
```

strace workflow: entering syscall

tracee

invokes a syscall

kernel

puts the tracee into SYSCALL-ENTER-STOP state

strace

- awakens
- fetches the syscall number and arguments
- applies filters
- may print something
- tells the kernel to let the tracee go on

kernel

- executes the syscall
- puts the tracee into SYSCALL-EXIT-STOP state

strace

- awakens
- may fetch the syscall return code and some arguments
- may print something
- tells the kernel to let the tracee go on

strace workflow: tampering with syscalls

- awakens
- fetches the syscall number and arguments
- applies filters
- **may tamper with the syscall number and arguments**
- may print something
- tells the kernel to let the tracee go on
- *the kernel executes the syscall*
- awakens
- may fetch the syscall return code and some arguments
- **may tamper with the syscall return code and arguments**
- may print something
- tells the kernel to let the tracee go on

strace signal injection

```
strace -a20 -P precious.txt unlink precious.txt
```

```
unlink("precious.txt") = 0  
+++ exited with 0 +++
```

```
strace -a20 -P precious.txt  
-e fault=unlink:error=EACCES:signal=ABRT  
unlink precious.txt
```

```
unlink("precious.txt") = -1 EACCES (Permission denied) (INJECTED)  
--- SIGABRT si_signo=SIGABRT, si_code=SI_KERNEL ---  
+++ killed by SIGABRT (core dumped) +++
```

strace syscall success injection

```
strace -P precious.txt unlink precious.txt
```

```
unlink("precious.txt")           = 0  
+++ exited with 0 +++
```

```
strace -P precious.txt -efault=unlink:retval=0  
unlink precious.txt
```

```
unlink("precious.txt")           = 0 (INJECTED)  
+++ exited with 0 +++
```

Questions?

homepage

<https://strace.io>

strace.git

<git://git.code.sf.net/p/strace/code.git>

<https://github.com/strace/strace.git>

mailing list

strace-devel@lists.sourceforge.net

IRC channel

[#strace@freenode](https://freenode.net/#strace)

GSoC 2016 project by Nahim El Atmani

<https://brokenpi.pe/tools/strace-fault-injection>